

# Natural under BS2000/OSD Batch Error Messages

This section lists error messages that may be issued by the Natural BS2000/OSD batch driver.

Unlike Natural system messages, the explanatory long texts to these error messages are only available in this document, not online.

---

## **NB20001 - NATURAL PARAMETER MODULE NOT FOUND**

Expl.	Natural parameter module in front-end and reentrant part not found.
-------	---

## **NB20002 - ERROR IN ENABLE CMP FOR BUFFER POOL MANAGER**

Expl.	An error has occurred when trying to enable the memory pool for the Natural buffer pool. The return code contains the SVC return code from register 15.
-------	---

## **NB20003 - ERROR IN REQUEST CMP FOR BUFFER POOL MANAGER**

Expl.	An error has occurred when trying to request the memory pool for the Natural buffer pool. The return code contains the SVC return code from register 15.
-------	--

## **NB20004 - ERROR IN ENABLE CMP FOR REENTRANT PART**

Expl.	An error has occurred when trying to enable the memory pool for the Natural load pool. The return code contains the SVC return code from register 15.
-------	---

## **NB20005 - ERROR IN ENABLE CMP FOR GLOBAL BUFFER POOL**

Expl.	An error has occurred when trying to enable the memory pool for the global buffer pool. The return code contains the SVC return code from register 15.
-------	--

## **NB20006 - ERROR IN LOAD OF REENTRANT PART OF Natural**

Expl.	An error has occurred when trying to load the Natural nucleus. The return code contains the SVC return code from register 15.
-------	---

## **NB20007 - ERROR IN ENABLE SERIALIZATION ITEM**

Expl.	An error has occurred when trying to enable the serialization item for the Natural start-up. The return code contains the SVC return code from register 15.
-------	---

## **NB20008 - ERROR IN ENQUEUE ACCESS REQUEST**

Expl.	An error has occurred when trying to enqueue the serialization queue for the Natural session initialization.
-------	--

**NB20009 - ERROR IN DEQUEUE ACCESS REQUEST**

Expl.	An error has occurred when trying to dequeue the serialization queue for the Natural session initialization.
-------	--

**NB20010 - UNABLE TO ESTABLISH ADABAS COMMUNICATION**

Expl.	The link module ADALNK or ADAUSER specified with the ADACOM generation parameter is neither linked to the Natural front-end nor could it be dynamically reloaded.
-------	---

**NB20020 - SESSION TERMINATED DUE TO SEVERE ERROR(S)**

Expl.	Session could not be initialized because resources were not available.
-------	--

**NB20022 - ERROR DURING INITIALIZATION OF NAF CMP**

Expl.	An error has occurred when trying to initialize the memory pool for Natural Advanced Facilities. No reports can be output via NATSPOOL.
-------	---

**NB20023 - NAF PARAMETER MODULE NOT LINKED IN**

Expl.	The Natural Advanced Facilities parameter module could not be located.
-------	--

**NB20025 - MODULE NATINV NOT LINKED FIRST TO NUCLEUS**

Expl.	The NATINV module was not included as the first one when linking the Natural nucleus.
-------	---

**NB20026 - MODULE NATLAST NOT LINKED TO THE NUCLEUS**

Expl.	The NATLAST module was not included in the link of the Natural nucleus. NATLAST must be included as the last module.
-------	--

**NB20027 - LINK ERROR FOR ADDRESS: *nnnnnnnn***

Expl.	The module " <i>nnnnnnnn</i> " specified in LINK or LINK2 of the NATBS2BATCH generation parameters could not be located. The module was probably not linked to the Natural TIAM front-end.
-------	--

**NB20030 - ERROR DURING READ OF DYNAMIC PARAMETER FILE**

Expl.	A DVS error has occurred when trying to read the parameter file.
-------	--

**NB20031 - ERROR DURING OPEN OF DYNAMIC PARAMETER FILE**

Expl.	A DVS error has occurred when trying to open the parameter file.
-------	--

**NB20032 - REENTRANT PART OF Natural BATCH DRIVER NOT FOUND**

Expl.	Reentrant part of batch driver found neither in the reentrant nor in the front-end part.
-------	--

**NB20040 - FRONT-END REENTRANT PART EXHIBIT A DIFFERENT ADDRESS MODE**

Expl.	The value (either 24 or 31) specified for the PARMOD parameter for the Natural reentrant part does not correspond to the one specified for the front-end part.
-------	--

**NB20041 - INVALID VERSION OF MODULE NATINV**

Expl.	Invalid version of module NATINV which is linked at first in the front-end part.
-------	--

**NB20042 - INVALID VERSION OF MACRO BS2STUB**

Expl.	Invalid version of module BS2STUB which is linked at in the front-end part.
-------	---